

**GEANT4**  
A SIMULATION TOOLKIT

Version 10.4-p02

# Primary Particle

Makoto Asai (SLAC)  
Geant4 Tutorial Course



NATIONAL  
ACCELERATOR  
LABORATORY



U.S. DEPARTMENT OF  
**ENERGY**

Office of Science


# Contents

---

- Introduction
- Built-in primary particle generators
  - Particle gun
  - Interfaces to HEPEVT and HEPMC
  - General particle source
- Pre-assigned decay

- Primary particle means particle with which you start an event.
  - E.g. particles made by the primary p-p collision, an alpha particle emitted from radioactive material, a gamma-ray from treatment head, etc.
  - Then Geant4 tracks these primary particles in your geometry with physics interactions and generates secondaries, detector responses and/or scores.
- Primary vertex has position and time. Primary particle has a particle ID, momentum and optionally polarization. One or more primary particles may be associated with a primary vertex. One event may have one or more primary vertices.

G4PrimaryVertex objects  
= {position, time}



G4PrimaryParticle objects  
= {PDG, momentum,  
polarization...}

- Generation of primary vertex/particle is one of the user-mandatory tasks.  
**G4VUserPrimaryGeneratorAction** is the abstract base class to **control** the generation.
  - Actual generation should be delegated to G4VPrimaryGenerator class. Several concrete implementations, e.g. G4ParticleGun, G4GeneralParticleSource, are provided.

- This class is one of mandatory user classes to **control the generation** of primaries.
  - This class itself **should NOT** generate primaries but **invoke `GeneratePrimaryVertex()`** method of primary generator(s) to make primaries.
- Constructor
  - Instantiate primary generator(s)
  - Set default values to it(them)
- **GeneratePrimaries()** method
  - Invoked at the beginning of each event.
  - Randomize particle-by-particle value(s)
  - Set these values to primary generator(s)
    - Never use hard-coded UI commands
  - Invoke **GeneratePrimaryVertex()** method of primary generator(s)
- Your concrete class of G4VUserPrimaryGeneratorAction must be instantiated in the **Build()** method of your **G4VUserActionInitialization**


```
MyPrimaryGeneratorAction::MyPrimaryGeneratorAction()
{
    G4int n_particle = 1;
    fparticleGun = new G4ParticleGun(n_particle);

    // default particle kinematic
    G4ParticleTable* particleTable = G4ParticleTable::GetParticleTable();
    G4ParticleDefinition* particle = particleTable->FindParticle("gamma");
    fparticleGun->SetParticleDefinition(particle);
    fparticleGun->SetParticleMomentumDirection(G4ThreeVector(0.,0.,1.));
    fparticleGun->SetParticleEnergy(100.*MeV);
    fparticleGun->SetParticlePosition(G4ThreeVector(0.,0.,-50*cm));
}

void MyPrimaryGeneratorAction::GeneratePrimaries(G4Event* anEvent)
{
    fparticleGun->SetParticleMomentum(G4RandomDirection());
    fparticleGun->GeneratePrimaryVertex(anEvent);
}
```

Constructor :  
Invoked only once


Invoked once  
per each event



**GEANT4**  
A SIMULATION TOOLKIT

Version 10.4-p02

Built-in primary particle generators



- Concrete implementations of G4VPrimaryGenerator
  - A good example for experiment-specific primary generator implementation
- It shoots one primary particle of a certain energy from a certain point at a certain time to a certain direction.
  - Various set methods are available
  - Intercoms commands are also available for setting initial values
- One of most frequently asked questions is :
  - I want “particle shotgun”, “particle machinegun”, etc.
- Instead of implementing such a fancy weapon, in your implementation of UserPrimaryGeneratorAction, you can
  - Shoot random numbers in arbitrary distribution
  - Use set methods of G4ParticleGun
  - Use G4ParticleGun as many times as you want
  - Use any other primary generators as many times as you want to make overlapping events



- In the constructor of your `UserPrimaryGeneratorAction`
  - Instantiate `G4ParticleGun`
  - Set default values by set methods of `G4ParticleGun`
    - Particle type, kinetic energy, position and direction
- In your macro file or from your interactive terminal session
  - Set values for a run
    - Particle type, kinetic energy, position and direction
- In the `GeneratePrimaries()` method of your `UserPrimaryGeneratorAction`
  - Shoot random number(s) and prepare track-by-track or event-by-event values
    - Kinetic energy, position and direction
  - Use set methods of `G4ParticleGun` to set such values
  - Then invoke `GeneratePrimaryVertex()` method of `G4ParticleGun`
  - If you need more than one primary tracks per event, loop over randomization and `GeneratePrimaryVertex()`.
  
- `examples/basic/B5/src/B5PrimaryGeneratorAction.cc` is a good example to start with.

```
void T01PrimaryGeneratorAction::
    GeneratePrimaries(G4Event* anEvent)
{ G4ParticleDefinition* particle;
  G4int i = (int)(5.*G4UniformRand());
  switch(i)
  { case 0: particle = positron; break; ... }
  particleGun->SetParticleDefinition(particle);
  G4double pp =
    momentum+(G4UniformRand()-0.5)*sigmaMomentum;
  G4double mass = particle->GetPDGMass();
  G4double Ekin = sqrt(pp*pp+mass*mass)-mass;
  particleGun->SetParticleEnergy(Ekin);
  G4double angle = (G4UniformRand()-0.5)*sigmaAngle;
  particleGun->SetParticleMomentumDirection
    (G4ThreeVector(sin(angle),0.,cos(angle)));
  particleGun->GeneratePrimaryVertex(anEvent);
}
```

- You can repeat this for generating more than one primary particles.

- Concrete implementations of G4VPrimaryGenerator
  - A good example for experiment-specific primary generator implementation
- G4HEPEvtInterface
  - Suitable to /HEPEVT/ common block, which many of (FORTRAN) HEP physics generators are compliant to.
  - ASCII file input
- G4HepMCInterface
  - An interface to HepMC class, which a few new (C++) HEP physics generators are compliant to.
  - ASCII file input or direct linking to a generator through HepMC.

- A concrete implementation of G4VPrimaryGenerator
  - Suitable especially to space applications

```
MyPrimaryGeneratorAction::
```

```
    MyPrimaryGeneratorAction()
```

```
{ generator = new G4GeneralParticleSource; }
```

```
void MyPrimaryGeneratorAction::
```

```
    GeneratePrimaries(G4Event* anEvent)
```

```
{ generator->GeneratePrimaryVertex(anEvent); }
```

- Detailed description






[Section 2.7 of Application Developer's Guide](#)

Square

Spherical






Cylindrical energy

Spherical volume with z biasing, isotropic radiation with theta and phi biasing, integral arbitrary point-wise energy distribution with linear interpolation








Source Energy Spectrum

Source X-Y distribution



Source X-Z distribution

Source Y-Z distribution



Source cos(theta)-phi distribution

Source theta/phi distribution







# Example commands of General Particle Source

## # two beams in a generator


```
#
# beam #1
# default intensity is 1 now change to 5.
/gps/source/intensity 5.
#
/gps/particle proton
/gps/pos/type Beam
#
# the incident surface is in the y-z plane
/gps/pos/rot1 0 1 0
/gps/pos/rot2 0 0 1
#
# the beam spot is centered at the origin and is of
# 1d gaussian shape with a 1 mm central plateau
/gps/pos/shape Circle
/gps/pos/centre 0. 0. 0. mm
/gps/pos/radius 1. mm
/gps/pos/sigma_r .2 mm
#
# the beam is travelling along the X_axis with
# 5 degrees dispersion
/gps/ang/rot1 0 0 1
/gps/ang/rot2 0 1 0
/gps/ang/type beam1d
/gps/ang/sigma_r 5. deg
#
# the beam energy is in gaussian profile
# centered at 400 MeV
/gps/ene/type Gauss
/gps/ene/mono 400 MeV
/gps/ene/sigma 50. MeV
```

(macro continuation...)

```
# beam #2
# 2x the intensity of beam #1
/gps/source/add 10.
#
# this is a electron beam
/gps/particle e-
/gps/pos/type Beam
# it beam spot is of 2d gaussian profile
# with a 1x2 mm2 central plateau
# it is in the x-y plane centred at the origin
/gps/pos/centre 0. 0. 0. mm
/gps/pos/halfx 0.5 mm
/gps/pos/halfy 1. mm
/gps/pos/sigma_x 0.1 mm
# the spread in y direction is stronger
/gps/pos/sigma_y 0.2 mm
#
#the beam is travelling along -Z_axis
/gps/ang/type beam2d
/gps/ang/sigma_x 2. deg
/gps/ang/sigma_y 1. deg
# gaussian energy profile
/gps/ene/type Gauss
/gps/ene/mono 600 MeV
/gps/ene/sigma 50. MeV
```



- Particle Gun
    - Simple and naïve
    - Shoot one track at a time
    - Easy to handle.
      - Use set methods to alternate track-by-track or event-by-event values.
  - General Particle Source
    - Powerful
    - Controlled by UI commands.
      - Almost impossible to control through set methods
    - Capability of shooting particles from a surface of a volume.
    - Capability of randomizing kinetic energy, position and/or direction following a user-specified distribution (histogram).
- 
- If you need to shoot primary particles from a surface of a volume, either outward or inward, GPS is the choice.
  - If you need a complicated distribution, not flat or simple Gaussian, GPS is the choice.
  - Otherwise, use Particle Gun.



**GEANT4**  
A SIMULATION TOOLKIT

Version 10.4-p02

Pre-assigned decay






- By default, when an unstable particle comes to its decay point, G4DecayProcess looks up the decay table defined in the G4ParticleDefinition of this particle type and randomly selects a decay channel.
- Alternatively, you may define a particular decay channel to G4PrimaryParticle.
  - Then, G4DecayProcess takes that channel without looking up the decay table and Lorentz-boost.
- Two major use cases.
  - Shooting exotic primary particle, e.g. Higgs. Geant4 does not know how to decay Higgs, thus you have to define the decay daughters.
  - Forcing decay channel for each particle, e.g. forcing a rare channel


# Pre-assigned decay products

- Physics generator can assign a decay channel for **each individual particle separately**.
  - Decay chain can be “pre-assigned”.
- A parent particle in the form of G4Track object travels in the detector, bringing “pre-assigned” decay daughters as objects of G4DynamicParticle.
  - When the parent track comes to the decay point, pre-assigned daughters become to secondary tracks, instead of randomly selecting a decay channel defined to the particle type. Decay time of the parent can be pre-assigned as well.

G4PrimaryParticle



G4Track



pre-assigned decay products

